

OPS User manual

OPS 5.0.0.0 / OPS-Pro 5.1.1

Wilco de Vries, Ferd Sauter

RIVM, 2020-10-07

Contents

1	Introduction.....	3
1.1	<i>Chemical characterisation of substances</i>	3
1.2	<i>Emissions</i>	4
1.3	<i>Meteorological statistics</i>	4
1.4	<i>Receptor characteristics</i>	5
2	OPS-Pro Graphical User Interface (GUI)	7
2.1	<i>What is OPS-Pro?.....</i>	7
2.2	<i>The Graphical User interface explained.....</i>	7
2.3	<i>Defining an OPS run with OPS-Pro.....</i>	8
2.4	<i>Defining a user-defined substance with OPS-Pro</i>	15
2.5	<i>View output files with OPS-Pro</i>	17
2.6	<i>Creating Files with OPS-Pro</i>	21
2.7	<i>Show Progress of an OPS-Pro run</i>	23
2.8	<i>OPS-Pro preferences</i>	24
2.9	<i>Modes for running OPS within OPS-Pro.....</i>	27
3	Input files.....	28
3.1	<i>Emission file</i>	28
3.2	<i>Receptor file.....</i>	32
3.3	<i>Diurnal Variation of Emission (DVE) file</i>	33
3.4	<i>Particle Size Distribution (PSD) file</i>	34
3.5	<i>Roughness length, land use, NL mask files</i>	35
3.6	<i>Chemical conversion rate files</i>	36
3.7	<i>Building effect files</i>	36
3.8	<i>Component properties file</i>	36
4	Output files.....	38
4.1	<i>PRNFILE / Report Output</i>	38
4.2	<i>PLTFILE / Tabulated output.....</i>	38
4.3	<i>PLTFILE / Map Output.....</i>	38
4.4	<i>APS format.....</i>	38
5	Running OPS at command line, source code, compiling	40
5.1	<i>OPS control file</i>	40
5.2	<i>Running OPS at the command line</i>	44
5.3	<i>Source code, compiling.....</i>	46
6	Examples	47
6.1	<i>Example 1, industrial point source.....</i>	47
6.2	<i>Example 2, industrial point source, user defined particle size distribution.....</i>	54

1 Introduction

This user manual is intended to help users define and run simulations with the air quality model OPS, developed at RIVM. OPS simulates the atmospheric process sequence of emission, dispersion, transport, chemical conversion and deposition and its main purpose is to calculate the concentration and deposition of pollutants (e.g. particulate matter, acidifying compounds like SO₂, NO_x and NH₃) for the Netherlands using a high spatial resolution (typically 1 x 1 km²). The model is, however, set up as a universal framework supporting the modelling of other pollutants (such as fine particles and persistent organic pollutants) and different resolutions.

OPS can be run as

- OPS-Pro (= OPS + Graphical User Interface)
- OPS-executable at a command line (Windows or Linux).

OPS-Pro users can skip chapter 5.

OPS-executable users can skip chapter 2.

Most users will run OPS-Pro, because the definition of input files is easier and input options in the GUI are restricted to possible combinations. The OPS-executable may be used by experienced users in batch mode, if f.ex. many simulations with slightly different input files are to be done. In this case, the user must take care that input is defined correctly.

Processes simulated with the OPS model as well as input and output parameters are extensively documented in the OPS-documentation¹, which can be downloaded from the OPS website www.rivm.nl/ops - "Documentatie" - "Uitgebreide modelbeschrijving". If needed, this manual will refer to this OPS-documentation.

This chapter defines the application area of the model in terms of chemical characterisation of substances, emission source types, source and receptor domain and time resolution.

1.1 Chemical characterisation of substances

The OPS model works with three groups of substances:

1. Acidifying substances (SO₂, NO_x, NH₃ and secondary products).
The properties of acidifying substances are defined within the model.
2. Non-acidifying (gaseous) substances
The group of non-acidifying substances uses a generic approach in which the properties of the substance are expressed in general terms such as:
 - a chemical conversion/degradation rate
 - a dry deposition velocity or a surface resistance
 - a wet scavenging ratio.

3. Particle-bounded substances.

A generic approach is followed for substances attached to particles in which the size distribution of the particles defines their atmospheric behaviour.

¹ F. Sauter, M. Sterk, E. van der Swaluw, R. Wichink Kruit, W. de Vries, A. van Pul : *The OPS model*.

1.2 Emissions

1.2.1 Source area

The model describes the transport of substances over greater distances, with wind fields generated from the temporal behaviour of wind direction, wind speed, atmospheric stability and mixing height averaged over meteorological regions in the Netherlands. The source area for this model has been set at a circle with a radius of 1000 km, with the Netherlands as the centre. The contribution of sources in this area to concentration and deposition in the Netherlands may be calculated for countries individually. The contribution of sources outside this area, but within Europe, can be estimated, but with less accuracy. The calculation of country-specific contributions from outside this area is probably not meaningful.

1.2.2 Source types

The OPS model distinguishes the following source types:

a. Point sources:

- source height ≥ 0 m
- negligible diameter
- with or without heat content or exit velocity.

b. Area sources:

- source height ≥ 0 m
- diameter ca. 10 m – 500 km
- square or circular
- with or without (average) heat content or (average) exit velocity
- standard deviation of the source height (from 0 m to average source height).

For both source types, a diurnal emission variation and a particle-size distribution can be specified, Emissions of either type can be input to the model in any number and in any combination.

For more information on emissions, see section '[Emission file](#)'.

1.3 Meteorological statistics

1.3.1 Meteorological time-scale

The OPS model calculates long-term average concentrations and depositions. In fact, the period for which the calculations are representative is entirely determined by the period for which the meteorological statistics have been made. At present, information is available for individual years since 1981. Long-term climatological data in the model is based on 2005 - 2014 data.

In addition to the standard (multi-year) averages, the OPS model can also calculate concentrations and depositions for shorter periods (specific year, season, month); special statistics will have to be compiled for such periods and these statistics are not part of the standard distribution of OPS.

1.3.2 Meteorological area

In the standard situation, the model interpolates the meteorological data of nearby regions to the position of the selected receptor. The user of the model can disconnect the automatic coupling of meteorological data and receptor position by selecting one of the six (standard) meteorological regions in the Netherlands or the Netherlands as a whole, see Figure 1.




Figure 1. Meteorological regions in OPS.

1.4 Receptor characteristics

Receptor points for calculating concentrations and depositions are characterised by their coordinates, height, land use type and roughness length. Receptor points can be chosen

- on a regular (Cartesian) grid, with a grid distance to be chosen. The domain may be pre-defined (the Netherlands) or defined by the user.
- For a number of specific locations to be defined by the user.

The latter option is especially useful when results have to be compared with observations. When the user selects grid output, OPS automatically generates multiple sub-receptors inside a grid cell in order to be able to compute a representative grid cell average. The number of sub-receptors goes to 1 with increasing source-receptor distance.

The default receptor height is 4 m within the OPS model, but the user can alter this height for specific receptors.

1.4.1 Receptor domain

The area for which concentrations and depositions can be calculated is determined by the size of the area for which meteorological parameters are known. Since the standard climatological data set used for this model is based on observations from the Royal Netherlands Meteorological Institute (KNMI), the maximum size of the receptor area becomes, in effect, the Netherlands and adjoining regions. Land use and terrain roughness data maps, covering only the Netherlands in great detail, also impose limitations.

1.4.2 Minimum source – receptor distance

This model does not explicitly take into account the direct influence of obstacles (e.g. forests, multiple buildings) on the dispersion. Instead, the general influence of obstacles is expressed in the terrain roughness variable, assuming that obstacles are homogeneously distributed over the

emission-receptor area. The shortest distance from a source for which this model may be used is therefore taken as a function of the terrain roughness length.

In flat terrain with no obstacles, the minimum distance is in the order of 20 m. For a terrain roughness > 0.1 m, the shortest distance is approx. 200 times the roughness length. The model generates no warnings if these rules are violated.

One should be aware that in the case of gridded receptor points in combination with point sources, the minimum source-receptor distance requirement cannot always be met, although the model approach of using sub-receptors, is designed to diminish the effect of these problems.

1.4.3 Restrictions

The OPS model is not intended for:

- Complex terrain (hilly and mountainous)
- Specific obstacle influences (multiple buildings, noise barriers, forest edges)
- Short-term averages (hour, day, calculation of percentiles)
- Complex chemistry (ozone formation).

2 OPS-Pro Graphical User Interface (GUI)

2.1 What is OPS-Pro?

OPS-Pro is the name given to the combination of the OPS model and a Graphical User Interface.


The graphical user interface lets you:

1. [Define an OPS run and subsequently run OPS](#)
2. [Define a user-defined substance](#)
3. [View and print OPS output, including map representations](#)
4. [Create emission files, emission attribute files and receptor files](#)
5. [Monitor the progression and status of jobs.](#)

This chapter can be skipped by users that prefer to run the OPS-executable from a command line.

2.2 The Graphical User interface explained


The Graphical User Interface consists of: (1) a menu bar, (2) a speed bar, (3) a task bar, (4) the input/output area and (5) a status bar.



The task bar enables you to select the different tasks (or functions) supported by the Graphical User Interface. The task chosen determines what is shown in the input/output area. It also determines which menu items and speed buttons are enabled. It is not possible to switch from one task to another before the first task has been completed, i.e. it is not possible to switch to **Show Progress** about midway in defining a run, and then return to **Define Run**.


The status bar is used to show the selected run mode of OPS, the name of the remote computer if OPS is running remotely, and the name of the file displayed when **View File** is selected.

2.3 Defining an OPS run with OPS-Pro

To define an OPS run, press **Define Run**. In the input/output area a tab book now appears. This tab book has four pages labelled **General**, **Emission**, **Receptor** and **Meteo & Roughness**. Job parameters must be specified on each page of the tab book. The buttons **Previous** and **Next** are used for navigating through the tab book. Pressing the **Finish** button will start OPS. If the required parameters are not all specified, an error message will pop up. The parameter values are saved in a so-called control file, which is stored in the output directory. The name of this file is composed of the run identifier and the extension '.ctr'. It is possible to save the parameters without running OPS. To do this, choose **File>Save** or press the  button. However, this can only be done after all parameters have been assigned their values.

Tip: To define a run that is very similar to a previously performed run, choose **File>Open**, or press the **Open** button and select the control file of that run. The parameter values of that run will be filled in. Adjust them and save the control file under a different name or press **Finish**.

2.3.1 General parameters



The screenshot shows the OPS-Pro 2020 application window with the 'Define Run' dialog box open. The dialog has a menu bar (File, Edit, Options, Help) and a toolbar. On the left, there is a vertical toolbar with icons for 'Define Run', 'View File', 'Create File', and 'Show Progress'. The main area of the dialog is divided into four tabs: 'General', 'Emission', 'Receptor', and 'Meteo and roughness'. The 'General' tab is selected and contains the following fields and options:

- Project name (max. 56 characters):** Example of OPS-Pro
- Run-identifier used for file naming (max. 76 characters):** Test
- Component:** NH3 (ammonium) - gas.
- Year:** 2020
- Unit of deposition:** mol/(ha.y)
- Output directory:** S:\QPS\Users\
- Include grids/tables in text output.
- Verbose output.
- Background execution.

At the bottom right of the dialog, there are three buttons: '< Previous', 'Next >', and 'Finish'. The status bar at the bottom of the window shows 'LSF run' and 'mil-ops'.

Project name


A text string (maximum 80 characters) used as header in the OPS Report output.

Run identifier

A text string used for naming the OPS output files. The name of a file is built up from the run identifier plus an extension, separated by a full stop. The extension depends on the type of output. The maximum length of the run identifier is limited to 76 characters.

The following characters – blank, slash, backslash, pipe symbol, comma, semi-colon, colon, <, >, apostrophe, plus sign and equal sign – are not permitted, so as to ensure deployment of OPS on the Unix platform.

Component

In the combo box titled **Component** you can select one of the pre-defined substances, or 'user-defined'. The physico-chemical characteristics of a pre-defined substance are built into the OPS model. If you select 'user-defined', the **Define Substance** dialogue pops up, in which you have to specify the name and molecular weight of the substance and, if applicable, the physico-chemical properties of the substance. You can inspect and edit already defined parameters by pressing the  button to the right of the combo box. See also section '[Defining a user-defined substance](#)'.

Year

The year to which the calculations apply. It is used in several ways.

1. For the automatic selection of the meteo statistics.
 - For a year in the past → meteo statistics for that same year. Meteo is available from 1981 onwards.
 - For a year in the future → long-term averaged meteo statistics for the period 2005-2014.
 - Automatic selection only takes place if 'Standard meteo – varying between receptors' is selected on the [Meteo & Roughness](#) page (the default type of meteo statistics). There also, the automatic selection can be overruled by the user.
2. For background concentrations of SO₂, NO_x and NH₃.
 - For a year in the past → background concentrations are used for that same year. Note that there are background maps available for some specific years (1984-1994-2005-2012) and that the average level of each map is calibrated for each year between 1981 and now.
 - For a year in the future → background concentrations are used from OPS runs with long-term averaged meteo, emissions 2020.
3. For chemical conversion rates of the EMEP model.
 - For a year in the past → EMEP chemical conversion rates are used for that same year. Note that prior to 2014, EMEP conversion rates are not available and OPS-Pro selects the old method, using parameterisations based on OPS background concentrations.
 - For a year in the future → EMEP chemical conversion rates are used from an EMEP run with meteo 2009, emissions 2030.


The reader is referred to the OPS-documentation for further details on the use of background concentrations and EMEP conversion rates.

Unit of deposition

You can choose between several deposition units in this combo box.

Output directory

The directory in which output will be stored. Each time an OPS job is defined from scratch, the default output directory specified in the **Preferences** dialog will be shown here. To select a different

directory, click on the  button to browse through your computer environment and select a directory.

Include grids/tables in Report output

Check this box if you want individual receptor values to be included in the Report output. This option is not suitable if the number of receptor points is large.


Verbose output

Standard parameters included in the Report output of OPS are concentration (also for secondary components if applicable), wet, dry and total deposition. Checking **Verbose output** means that additional parameters will be printed: effective deposition velocity (also for secondary components if applicable), roughness length and land use.

Background execution


Checking **Background execution** will run OPS in the background.

2.3.2 Emission parameters




The screenshot shows the 'Emission' tab in the OPS-Pro 2020 software. The 'Emission file' field contains the path 'S:\OPS\Data\Input\Bronbestanden\NL\nh3\2015\gcn2018\NH3_15_'. Below it are fields for 'File with user defined diurnal variations', 'File with user defined particle size distributions', 'Selection of target group' (set to '<all>'), and 'Selection of country/region' (set to '<all>'). There is a checkbox for 'Apply emission correction factor' which is unchecked. At the bottom, there are checkboxes for 'Verbose output' (unchecked) and 'Background execution' (checked). Navigation buttons '< Previous', 'Next >', and 'Finish' are visible.


Emission file

The file in which emission sources and their characteristics are specified. The  button at the right of this text box allows you to browse through your computer environment to find and select an emission file.

File with user-defined diurnal variations

As soon as you have specified the emission file name, OPS-Pro scans this file to see whether it contains codes for a personalised 'Diurnal Variation of Emission'. If so, this normally disabled text box becomes enabled. You will have to specify the name of the file in which the distributions coupled to these codes are described. The  button at the right lets you browse through your computer environment to find and select the appropriate file. See section '[Diurnal Variation of Emission \(DVE\) file](#)'.

File with user-defined particle size distributions

As soon as you have specified the emission file name, OPS-Pro scans this file to see whether it contains codes for a personalised 'Particle Size Distribution'. If so, this normally disabled text box becomes enabled. You must specify the name of the file in which the distributions coupled to these codes are described. The  button at the right lets you browse through your computer environment to find and select the appropriate file. See section '[Particle Size Distribution \(PSD\) file](#)'.

Selection of target group (sector)

As soon as the emission file is specified, OPS-Pro scans this file to determine whether it contains emissions for more than one target group. If so, the identification numbers of the target groups are listed in the combo box. You can either select one of these target groups or indicate <all>. Only emissions for selected target groups are used in this specific run. Default is <all>.

Selection of country/region

As soon as the emission file is specified, OPS-Pro scans it to determine whether it contains emissions for more than one country or region. If so, the identification numbers of the countries or regions are listed in the combo box. You can either select one of these countries/regions or indicate <all>. Only emissions for selected countries/regions are used in this specific run. Default is <all>.

Apply emission correction factor

Checking this box enables you to set an emission correction factor. Emissions in the emission file will all be multiplied by this factor. This is useful, for instance, in situations where the emissions are yearly averages and calculations are done for a specific period in one year, with emissions not homogeneously distributed over that year.

2.3.3 Receptor parameters

OPS-Pro 2020

File Edit Options Help

General Emission **Receptor** Meteo and roughness

Receptortype

- Midpoints of the grid cells of a grid covering the Netherlands.
- Midpoints of the grid cells of a grid specified by the user.
- Defined in a file.

Grid specification

X-coordinate of grid midpoint (m): 128730 Y-coordinate of grid midpoint (m): 432780 Grid cell dimension, both directions (m): 500

Number of cells horizontally: 15 Number of cells vertically: 15 Include gridpoints outside the Netherlands.

Verbose output.
 Background execution.

< Previous Next > Finish

LSF run mil-ops

Receptor type

OPS-Pro offers three means to specify receptor points:

- using midpoints of the grid cells of a grid covering the Netherlands (the default).
- Using midpoints of the grid cells of a grid specified by the user.
- Using locations defined in a file.

When "Using midpoints of the grid" is selected

X-coordinate (XCENTER)

The X-coordinate (in metres) of the centre of the grid in the **RDM**² coordinate system. This is only required for a user-defined grid. Contrary to previous versions of OPS, it is no longer allowed to enter X = 0, when calculations for a single source are performed. Note that the grid centre may lie at a grid cell corner (NCOLS and NROWS even) or grid cell edge (one of NCOLS or NROWS even) or in the centre of a grid cell (NCOLS and NROWS odd).

Y-coordinate (YCENTER)

The Y-coordinate (in metres) of the centre of the grid in the **RDM** coordinate system. This is only required for a user-defined grid. Contrary to previous versions of OPS, it is no longer allowed to enter Y = 0, when calculations for a single source are performed.

² RDM stands for 'Rijksdriehoeksmeting', the reference coordinate system in the Netherlands.

Number of cells horizontally (NCOLS)

Only required for a user-defined grid. The maximum number equals 9999.

Number of cells vertically (NROWS)

Only required for a user-defined grid. The maximum number equals 9999.

Grid-cell dimension (RESO)


The size of the grid cells (in metres). Grid cells in OPS are always squares.


The smallest grid-cell size is 500 metres for a grid covering the Netherlands and 1 metre for a user-defined grid.

Include grid cells outside the Netherlands

In the default situation no calculations are performed for grid cells outside the Netherlands. Check this box for calculations to be performed for these cells as well. This only applies to the default receptor type (a grid covering the Netherlands).

When "Defined in a file" is selected




The coordinates of the receptor points are specified in a file, along with the sequence number and name of the receptor points. If this option is chosen, you can select one of the files delivered with OPS-Pro or specify your own file. You can browse through your computer environment and select a receptor file by pressing the  button.

The points specified in a receptor file are usually not on a raster (although all the points specified in the files delivered with OPS-Pro are). Here, a warning must be given. If the points specified in a receptor file are on a raster and "Receptorpoints are on a raster" is selected, the results for these points will differ from the results obtained if the same points are specified by a grid. This is because OPS-Pro selects, from the available roughness length maps, the one with the highest resolution when receptor points are specified in a file, and a resolution comparable to the output resolution when the receptor points are specified by a grid.

For receptor points defined in a file and not on a raster, OPS computes concentrations at a specific location; for other receptor types, OPS computes grid cell averaged concentration (using sub receptors).

More information on the contents of a receptor file can be found in the section '[Receptor file](#)'.

2.3.4 Meteo & Roughness parameters



Type of meteo statistics

OPS-Pro offers three choices for meteorological statistics:

- Standard meteo - varying between receptors
- Standard meteo - the same for all receptors
- Special meteo defined in a file.

Standard meteo - varying between receptors

This option, which is the default, means that for each receptor point a specific meteo statistic is calculated by interpolation from the average meteo statistics for 6 subregions of the Netherlands.

Standard meteo - the same for all receptors

This option means that the same meteo statistics are used for all receptor points. This is either the average statistics for the Netherlands or for one of the 6 subregions delivered with OPS-Pro.

Special meteo defined in a file

As with the second option, the same statistics are used for all receptor points. However, the statistics are not taken from one of the standard files that come with OPS-Pro, but from a file provided by the user. Although this option is offered, external users cannot produce meteo statistics themselves.

Meteorological period and region

The period (and region) to which the meteo statistics should apply is selected from this combo box. If the year to which the OPS calculations apply is already selected on the **General** page and if the type of meteo statistics is 'Varying between receptor points', OPS-Pro automatically selects the meteo period. This automatic selection can be overridden by the user.


Roughness length options

OPS-Pro offers two options for specifying the roughness length z_0 . In the first option (the default), OPS-Pro uses a receptor specific z_0 whose value is obtained from a roughness grid forming part of OPS-Pro. In the other option, the user supplies a z_0 value to be used for all receptor points. This value must be between 0 and 3 metres. In this case, OPS automatically sets the land use type to grass.

Roughness length and land use

OPS-Pro supports the use of more than one type of roughness grid, for instance, z_0 based on current land use or z_0 based on future land use. At present, only z_0 based on current land use is delivered with OPS-Pro. Each type of roughness grid is available in several resolutions; more information on how OPS-Pro selects a certain resolution can be found in section '[Roughness length, land use, NL mask files](#)'.

2.4 Defining a user-defined substance with OPS-Pro

A user-defined substance may be defined in the **Define component** dialog, accessed by selecting **User defined** in the **Component** combo box on the **General parameters** tab or press the  button to the right of the **Component** combo box. This will pop up the **Define component** dialog.

Three choices of substance are offered:

- Particle-bound
- Gaseous, no conversion and deposition
- Gaseous, with conversion and deposition.

With the first two options, only the name of the substance and the molecular weight has to be specified, while with the third option, **parameters for dry and wet deposition and chemical conversion** must also be specified. The **Define component** dialog will be enlarged for this purpose.

Dry deposition

The dry deposition process may be parameterised in two ways: either by surface resistance, R_c , or overall dry deposition velocity, v_d . The best parameterisation is obtained with R_c because the deposition velocity can then be differentiated according to atmospheric stability. If the user specifies v_d , the model will estimate a corresponding average R_c value.

Valid values for the R_c range from 0 to 999999.9 $\text{s}\cdot\text{m}^{-1}$ and for v_d from 0.000001 to 0.034 $\text{m}\cdot\text{s}^{-1}$.

Wet deposition

Wet deposition may occur in two ways, wash-out and rain-out.

Wash-out (below-cloud scavenging)

Wash-out is the removal of the substance from the plume by rain falling through it. Wash-out occurs only with highly soluble gases and particles and is mainly important at short distances from the source.

The wash-out process is considered either to be fully irreversible (for most substances) or fully

reversible (e.g. for SO₂). In the case of reversible wash-out, material disappears again from a raindrop when this drop comes into cleaner ambient air (e.g. below a smoke plume).

Rain-out (in-cloud scavenging)

Rain-out is the removal of the substance from clouds by rainfall, playing a dominant role in wet deposition at greater distances from the source when the plume interacts wholly or partially with clouds.

The wash-out process is determined by the gaseous diffusion coefficient of the substance in air (D_g), while the rain-out process is described by the average ratio between the concentration in rainwater and the concentration in air. The best model description of the wet deposition process is obtained when the user specifies both rain-out and wash-out. In this case the user must also indicate whether the wash-out process is reversible.

If the required information is not available, alternatives for specifying the wet deposition process are the scavenging ratio (-), the average ratio of concentrations in rainwater and air and the average scavenging coefficient (%.h⁻¹). If the wet deposition process is specified by a scavenging ratio or coefficient, the OPS model will estimate D_g from the molecular weight of the substance.

Valid values for the rain-out ratio range from 0 to 9999999; D_g must be in the range of 0 to 1 cm².s⁻¹. Valid values for the scavenging coefficient range from 0 to 9999 %.h⁻¹ and for the scavenging ratio from 0 to 9999999.

Chemical conversion rates


Chemical conversion rates (in %/h) describe the rate of change of the primary component, when it is chemically converted into a secondary component, e.g. SO₂ → SO₄²⁻. For SO₂, NO_x and NH₃, default chemical conversion rates are yearly averaged conversion rates taken from a grid generated by the EMEP model for the current simulation year. Note that prior to 2014, EMEP conversion rates are not available and OPS-Pro selects the old method, using parameterisations based on OPS background concentrations.

For a user specified component, the user must specify a light-independent (CONVRATE) and light-dependent (LDCONVRATE) conversion rate. 'Light-independent' specifies the base conversion rate, while 'light-dependent' specifies the gain per unit radiation. The total chemical conversion rate = CONVRATE + LDCONVRATE x Q, with Q = global radiation [W.m⁻²].

Valid values for the light-independent conversion range from 0 to 999.9 %.h⁻¹ and for light-dependent from 0 to 99.99 %.h⁻¹ per W.m⁻².

2.5 View output files with OPS-Pro

The output of OPS runs can be viewed by pressing **View File** in the task bar. A tab book of two pages, named 'Report' and 'Map', will be displayed in the **input/output** area. More information on the contents and format of these files can be found in the section '[Output files](#)'.



2.5.1 View Report output of OPS

Click on the tab labelled **Report**; choose **File>Open** (or press the **Open** button) and select the text file for display in the **Open** dialog. The name of the displayed file is shown in the Status bar.

2.5.2 View Map output of OPS

Click on the tab labelled **Map** and proceed in the same way as for Report output. Use the **Type** combo box to choose between the different fields contained in the file (concentration, dry deposition, wet deposition, total deposition and, in case the component is SO₂, NO_x or NH₃, the concentration fields of one or more of the secondary components). The name of the displayed file is shown in the Status bar.

The layout of the map can be changed by pressing **Layout**.

The **View File** task is automatically started with the right arguments

- after a successful foreground run of OPS if you answer 'Yes' to the question: '**View output files**'
- if you choose **View Output** in the **Show Progress** window.

Remarks:

- Though '**Report**' is primarily intended to view the Report output of OPS, it is also possible to view other ASCII file types. To do so, set the appropriate file type in the **Files of Type** combo box of the **Open** dialog.
- You *cannot* change the contents of a text file.
- Map output is only available for gridded receptor points.

2.5.2.1 *Changing the layout of a map*

The standard layout of the map can be changed by pressing **Layout**. This opens the **Layout** dialog in which you can:

1. [Change map titles and add text](#)
2. [Change classification type, class limits and colour palette](#)
3. [Add boundaries to a map.](#)

Press **OK** to update the display and close the **Layout** dialog, **Cancel** to ignore changes and close the dialog or **Apply** to preview the applied changes without closing the **Layout** dialog.

2.5.2.2 *Change map titles and add text*

Changing map titles and adding free text is done on the **Text** page of the **Layout** dialog.

2.5.2.3 *Change classification type, class limits and colour palette*

Classification type, class limits and colour palette can be set on the **Classification** page of the **Layout** dialog.

Classification type can be either linear or logarithmic. Class limits of the logarithmic type are always determined by OPS-Pro. For the linear type, users can set their own class limits by un-checking the **auto** box in the **Settings** panel. The maximum number of classes is 5, both for linear and logarithmic classification.

The user can select one of 5 pre-defined colour palettes by pressing the **Change** button in the **Colour Palette** panel.

2.5.2.4 *Add boundaries to a map*

For purposes of geo-referencing, boundaries can be drawn on the map. Boundaries are set on the **Boundaries** page of the **Layout** dialog.

To select a boundary, click on the name of that boundary in the **Available** box and press the right arrow key. The selected boundary will show up in the **Selected** box. To select multiple boundaries all at once, press the CONTROL key, click on the desired boundaries and press the right arrow button. To select multiple boundaries in a continuous list, press the SHIFT key, click on the first boundary in the list, then on the last boundary and press the right arrow button. To select *all* available boundaries all at once, press the double right arrow button.

To *remove* boundaries from the **Selected** box, follow these steps in reverse order.

Explanation of the boundary names:

- nl : The Netherlands
- nl_corop : The Netherlands divided into COROP areas
- nl_gem : The Netherlands divided into municipalities
- nl_prov : The Netherlands divided into provinces
- nl_verz : The Netherlands divided into acidification areas.

The information will not be saved; you can only make a screen dump and print it.

2.6 Creating Files with OPS-Pro

OPS-Pro assists in the creation of emission files, emission attribute files and receptor files. This section provides information on the use of this facility. Information on the meaning and content of these files and their structure is given in the chapter '[Input files](#)'.

Important note: **Create file** is meant to provide assistance to make input files for OPS for relative simple simulations. Not all possible inputs, which are available for OPS, can be made using **Create File**. For a full list of possibilities, one is referred to the chapter '[Input files](#)'.

To start the Create File facility press the **Create file** button in the **task bar**. Next, select the file type you want to create. In the **input/output** area, you will see a number of boxes, one for each variable of the specified file type. Values are entered per record. Type the variable values in these boxes, or select a value from the list of possible values. Pressing ENTER will place the cursor in the next box. After all variables of a record are entered, pressing ENTER will cause the cursor to jump to the next record.

OPS-Pro checks the values entered to see if they are in the valid data range. In addition, OPS-Pro checks whether the DVE and PSD distributions add up to 100%.

Existing files can be opened for modification, although this is not true for emission files.

You can scroll through the records of a file and insert and delete records by means of the navigation bar.



 **First**

Positions the record pointer on the first record

 **Fast backward**

Positions the record pointer ten records back (or on the first record)

 **Previous**

Positions the record pointer on the previous record (or on the first record)

 **Next**

Positions the record pointer on the next record

 **Fast forward**

Positions the record pointer ten records forward (or on the last record)

 **Last**

Positions the record pointer on the last record

 **Insert**

Inserts a new record in the current position

 **Delete**

Deletes the current record.

Additional controls for creating emission files

In addition to text boxes there are other controls to specify the characteristics of an emission source.

- 1 Combo boxes from which a value must be chosen for Diurnal variation, Particle size, Target group, Region/Country and Component name.
 - OPS-Pro shows a description of the possible values for each of these inputs, but places a corresponding numeric code in the emission file. The relationship between codes and description is laid down in so-called definition files, which can be found in the subdirectory *Definitions* of the **Data directory**. The definitions may be changed for personal use (if the Data directory is shared by several users, it is, of course, the data manager who modifies the corresponding files).
 - Note that you cannot mix emission records for different components into one file. The user must supply the correct emission file for the component for which the run is defined; the component name is not checked by OPS-Pro.
- 2 Check boxes labelled '**User-defined**' for diurnal variation and particle size. Check these boxes if you want to use your own definitions instead of the definitions that come with OPS-Pro. After checking, the **Open** dialog will pop up; here, you have to specify the file(s) in which these personal definitions are described. User-defined definitions apply to all sources; in other words, it is not possible to take up user-defined and standard definitions in the same emission file. Therefore if you want to use personal definitions, you must check '**User-defined**' at the very first record.

3 Check box 'Gaseous'.


If the component is not one of the pre-defined components that come with OPS-Pro, you must indicate, using this check box, whether the component is gaseous or not. In the case of a pre-defined component, OPS-Pro determines the checking of this box and subsequently disables it. If this box is checked, the 'Particle size' combo box becomes disabled.

4 Copy previous button.

This control copies the values of the previous record, practical when emission sources differ only in their coordinates and strength.

2.7 Show Progress of an OPS-Pro run

The status of jobs running in the **background (local or remote)** can be accessed by pressing **Show Progress**. A table will be displayed in the **input/output** area that lists the status of all jobs in the system.



Job-id

The identifier of the job. This is the same as the **run identifier** used in defining the job.

Remote

Indicates whether the job is running or has run on a remote computer.

Submit time

Time when job was submitted.

Status

The status of the job. Values are UNKNOWN, RUNNING, CANCELLED, ERROR and OK.

Unknown is displayed when OPS-Pro cannot (yet) obtain information about the job, RUNNING when the job is not yet completed, CANCELLED if the job is killed by the user, ERROR when the job is finished in error and OK when the job is finished without error.

Progress

The percentage done. UNKNOWN is displayed when the status is unknown and READY when the job is finished, with or without error.

Kill

Running jobs, started by mistake or with wrong parameters, can be killed by pressing **Kill**.

Remove

Jobs that are finished - with or without error – or killed can be removed from the system. To do so, click on the row with the appropriate job and then press **Remove**. It is not yet possible to remove multiple jobs simultaneously. As long as a job is not removed from the system, it is not possible to use the same run identifier for another job to be run in the background.

Refresh

The status information is automatically checked with a frequency set in the **Preferences** dialog. Press **Refresh** to enforce updating of the status information.


View Error

If a job is finished in error, the error message can be viewed by selecting the appropriate job and then pressing **View Error**.

2.8 OPS-Pro preferences

The **Preferences** dialog, accessed by the menu option **Edit>Preferences**, allows the user to set a number of items. It consists of two pages.

On the page **General** the path to the files read and produced by OPS are set.



Data directory

The directory in which data needed by OPS are stored (land use, roughness length, etc.). Initially, the data directory is set to the path specified during the installation of OPS-Pro. If, after installation, OPS-data are moved to another location, for instance, to a network computer, the data directory must be set to this new value.

Default meteo directory

The directory in which the meteo statistics are stored. Initially, the meteo directory is set to the path specified during installation of OPS-Pro. If, after installation, the meteo statistics are moved to another location, for instance, to a network computer, the meteo directory must be set to this new value.

Default receptor directory

The directory in which OPS-Pro looks for receptor files every time a new job is defined from scratch.

Default emission directory

The directory in which OPS-Pro looks for emission files every time a new job is defined from scratch.


Default output directory

The directory in which OPS output (including the control file) is stored by default. When defining an OPS job, the actual directory in which the output is saved can be set on the **General** (parameters) page.

Status check interval

The frequency with which OPS-Pro looks for the status of jobs running in the background.

On the page **Remote execution** you can set preferences for jobs run at a remote system.



Run OPS on remote computer


It is possible to run OPS on a remote computer or a cluster, i.e. a computer other than the one on which the graphical user interface runs. If you want so, please contact your system administrator for further instructions.

Set Default

Set the default system for running remote jobs.

Add

Add information on hostname, username and password of a remote system on which jobs can be executed.



Edit

Change information for a specific remote system.

Delete

Delete information for a specific remote system.

2.9 Modes for running OPS within OPS-Pro

OPS can be run in any one of four modes:

- 1 Locally in the foreground
- 2 Locally in the background
- 3 Remote in the foreground
- 4 Remote in the background

The latter two modes are available only after the system has been set up for remote execution of OPS.

'Foreground' means that the user must wait until the job has finished before a new job can be defined or run. If a job is started in the background, one or more new job(s) can be defined and run immediately after the job is started. The progress of a job started in the foreground is displayed by means of a Progress bar. The status and progress of a job running in the background can be retrieved using the function **Show Progress**. After the successful completion of a foreground job, users are asked whether they want to view the output of that job. Foreground execution is the default. Background execution is requested by checking the **Background execution** box, which is available on all pages of the **Define run** tab book.

Local execution means that OPS runs on the same computer as the one on which OPS-Pro runs. In the case of remote execution, OPS is started on a network computer, typically known as a 'calculation server'. Because simultaneous running of many large jobs locally will slow down the user's system, it is advised to request remote execution in such a case. Remote execution can be selected in the **Preferences** dialog. Whether OPS runs (temporarily) at the local level or remote is displayed in the Status bar of the interface.

When remote execution applies, all data used by OPS must reside on one or more remote computers and these data must be accessible to the system on which OPS will be run. In the case of local execution the data may all reside locally or remote, or both locally and remote.

Once remote execution is selected, it will apply to all subsequent jobs until it is de-selected in the **Preferences**. Local execution can be enforced temporarily by the **Options>Temporarily local run**. This is suitable if using a control file with for instance an emission file on your local computer.

3 Input files

OPS has the following input files:

- [3.1 Emission file](#)
- [3.2 Receptor file](#)
- [3.3 Diurnal Variation of Emission \(DVE\) file](#)
- [3.4 Particle Size Distribution \(PSD\) file](#)
- [3.5 Roughness length, land use, NL mask files](#)
- [3.6 Chemical conversion rate files](#)
- [3.7 Building effect files](#)
- [3.8 Component properties file.](#)

The emission file is always needed. The presence of the other files depends on the choices made in defining the OPS job.

3.1 Emission file

3.1.1 Introduction

The emission file describes the location of the sources, their strength and basic characteristics in a number of variables listed below.

variable	description	variable	description
snr	source number	s	standard deviation source height
x	X-coordinate	dv	diurnal variation of emission
y	Y-coordinate	cat	source category number
q	source strength	area	source area number
hc	heat content	ps	particle size distribution
h	stack height	comment	comment string for user
r	source diameter		

In section [3.1.3](#), a more detailed description of these emission characteristics is given. For special situations described below (plume rise due to momentum, building effect), we may have other parameters that are to be included in the emission file, see sections [3.1.4](#) and [3.1.5](#).

3.1.2 Data format

Depending on whether plume rise due to momentum and/or the building effect is taken into account, there are different formats of an emission record.

Version without BRN-VERSION number (version 0)

```
snr      x      y      q      hc      h      r      s      dv      cat      area      ps      comment
1 176000 442000 0.1 0 2 0 0 4 1 4 0 NH3
```

! BRN-VERSION 1

```
!snr      x      y      q      hc      h      r      s      dv      cat      area      ps      comment
1 176000 442000 0.1 0 2 0 0 4 1 4 0 NH3
```

! BRN-VERSION 2

```
!snr      x      y      q      hc      h      r      s      D_stack  V_stack  Ts_stack  dv      cat      area      ps      comment
1 176000 442000 0.1 0 2 0 0 1.0 10.0 -999.0 4 1 4 0 NH3
```

! BRN-VERSION 4

```
!snr      x      y      q      hc      h      r      s      D_stack  V_stack  Ts_stack  dv      cat      area      ps      L      W      H      O      comment
1 176000 442000 0.1 0 2 0 0 1.0 10.0 -999.0 4 1 4 0 40 20 5 0 NH3
```

basic

momentum plume rise

building effect

- All variables must be separated by spaces or tabs.
- A missing value (unspecified) is indicated by -999.0. Note that heat content hc and effluent temperature Ts_stack cannot be specified both, one of them must be left unspecified.
- The last column (`comment`) is for your own reference and is not read by OPS.
- The emission records must be preceded by a header with BRN-VERSION n and a record with parameter names. More header records with additional information are allowed. All header lines should start with "!" (from BRN-VERSION 1 onwards).
- It is not allowed to use records with different formats in one emission file.
- The unnumbered version uses a fixed format record, which is still read by OPS (but not recommended).

In Fortran notation:

I4, 2I8, E10.3, F7.3, F6.1, I7, F6.1, 4I4, 2x, A12 for RDM coordinates (x,y in metres)

I4, 2F8.3, E10.3, F7.3, F6.1, I7, F6.1, 4I4, 2x, A12 for geographical coordinates (longitude, latitude in degrees).

BRN-VERSION 3 is not supported anymore.

The **Create File** function in OPS-Pro assists in creating emission files. However, this function is not suitable for emission files with many sources and it creates only basic emission files (without exit velocity or building characteristics). It is possible to create other types of emission files with an Excel macro *maak_bronbestanden*; this macro can be downloaded from the OPS website.

3.1.3 Basic emission characteristics

Source number snr

An identification number of the source. Field is not used by OPS.

Source X-coordinate x

The X-coordinate (longitude) of the source. The position of a source can be fixed in RDM coordinates (unit metres; integer value) or in geographical coordinates (unit degrees; decimal notation). Note that the two coordinate systems may be mixed in one file.

Source Y-coordinate y

The Y-coordinate (latitude) of the source. The position of a source can be fixed in RDM coordinates (unit metres; integer value) or in geographical coordinates (unit degrees; decimal notation).

Source strength q

The strength of the source is the average emission rate over the total period considered in $g\ s^{-1}$. If you want to calculate an annual averaged concentration, you must also use an annual averaged emission.

Heat content hc

The heat content of the source is used to permit calculation of the effective plume height under different climatological conditions. The unit is megawatt. When the heat content is not constant, an emission-weighted average can be chosen. Alternatively, you can use the optional values for stack diameter D_stack , exit velocity V_stack and effluent temperature Ts_stack and let OPS compute the

heat content (in this case set the heat content here to the missing value -999.0) or set the value for Ts_stack to -999.0 and compute the heat content h_c [MW] yourself from:

$$h_c = \rho_0 C_{p,0} V_0 (T_s - T) 10^{-6} \text{ MW}$$

with

V_0 : normalised (at T_0) volumetric flow rate of the flue gas [$\text{m}_0^3 \text{ s}^{-1}$] = $\pi(D_s/2)^2 V_s T_0/T_s$

T : ambient temperature at stack height [K]

T_s : temperature of the flue gas [K]

T_0 : temperature for which the flow rate is normalised (= 273 K)

ρ_0 : reference density of air (= 1.293 kg m^{-3})

$C_{p,0}$: reference specific heat of air (= 1005 $\text{J kg}^{-1} \text{ K}^{-1}$)

Note that if heat content and D_s , V_s are given, and if the user specifies an unrealistic high value of the heat content, such that the heat content cannot be reached within the volume flux given, then OPS will issue an error message and stop. In OPS, this will take effect if the corresponding temperature of the effluent gas is higher than $T_{s,max} = 2000 \text{ C}$, i.e. at

$$h_{c,max} = \rho_0 C_{p,0} \pi \left(\frac{D_s}{2}\right)^2 V_s (T_0/T_{s,max}) (T_{s,max} - T) 10^{-6} \text{ MW}$$

For a number of parameter settings of D_s and V_s , this maximal value of heat content $h_{c,max}$ can be seen as a dotted line in Figure 2.




Figure 2: Stack temperature Ts_stack [C] as function of heat content h_c [MW]. Dotted lines correspond with maximal effluent gas temperature = 2000 C in OPS. Ambient temperature = 20 C.

Stack height h

This is the height (in metres) of the physical outlet above the ground. For surface sources, the average emission height must be entered here.

Source diameter r

Surface sources are treated by OPS as square in shape, with the source diameter the length of a side of the square. It is also possible to start from a circular source by entering the diameter as a negative number. For point sources, the source diameter is 0 m; the dimension of the chimney exit (stack diameter) should definitely **not** be entered as a source diameter. Although the model yields the same results for a surface source with a diameter approaching zero and a point source, it is advisable to input a source diameter greater than zero only when the horizontal dimension of the source is really of importance.

Standard deviation source height s

This parameter is only relevant for surface sources. A surface source is generally a collection of unspecified point sources, each of which may produce emissions at a different height. The average height is taken to be the stack height of a surface source, and the parameter concerned here is the standard deviation of this average height. The vertical distribution of emissions is especially important for calculating concentrations within the surface source concerned.

Diurnal variation of emission code dv

The model may take account of the fact that the emissions from certain sources exhibit a characteristic daily variation. The user can choose from a set of standard distributions of emissions throughout the day or can choose a user-defined diurnal variation. More information in section '[Diurnal Variation of Emission \(DVE\) file](#)'.

Source category number cat

This number can be used to distinguish various categories (e.g. economic sectors). OPS offers the possibility of selecting a certain category (*target group*) from an emission file, so that the contribution made by that category can be calculated separately. OPS does not use the source category number for anything else.

Source area number $area$

This number can be used to make a spatial subdivision of the sources possible. OPS-Pro offers the possibility of selecting a certain source area (*country / region*) from an emission file, so that the contribution made by that area can be calculated separately. OPS does not use the source area number for anything else.

Particle-size distribution code ps

To model different processes that depend on particle size, OPS requires the emission to be distributed over different particle-size classes. The user can choose from a set of standard particle-size distributions or can choose a user-defined size distribution. More information in section '[Particle Size Distribution \(PSD\) file](#)'.

Comment

The comment string is for your own reference and is not used by OPS. OPS-Pro **Create File** puts here the component name chosen, but the user should provide the correct emission file for the

simulation at hand. As pointed out before, emission records for different components cannot be mixed in one file.

3.1.4 Plume rise

Due to heat or momentum, the effluent may exit the stack with a certain velocity, thus causing the plume to rise above the stack tip. This plume rise is an important parameter in the computation of concentrations, especially near the source. Four parameters are used in the plume rise parameterisation.

Stack diameter D_s

The inner diameter of the stack in metres. Note that this is **not** the same as the (area) source diameter r specified earlier. Short name D_s .

Exit velocity V_s

The exit velocity of the effluent in m/s. Short name V_s .

Effluent temperature T_s

The temperature of the effluent as it leaves the stack in degrees Celsius. Short name T_s .

There are three ways to specify these parameters in the emission file:

1. specify only Q_w and do not specify D_s , V_s , T_s .
2. Specify Q_w and D_s , V_s , but not T_s . In this case, T_s is computed by OPS.
3. Specify D_s , V_s , T_s , but not Q_w . In this case, Q_w is computed by OPS.


In case 1, only plume rise due to heat is taken into account. In cases 2 and 3, both plume rise due to heat and momentum are computed and OPS uses the dominant type of plume rise (either due to heat or due to momentum). A variable is left unspecified if it is set to -999.0 in the emission file.

3.1.5 Building effect

The influence of a single building on the emitted plume can be included in the calculations of the concentration and deposition. More information on the building effect module in OPS and its limitations can be found in a separate document on the building effect in OPS (download from www.rivm.nl/ops).

Building parameters L , W , H , O

Parameters that are needed for the building effect are the building dimensions L (length), W (width) and H (height) in metres and the building orientation O (in degrees, see figure below).



Inclusion of a building effect is restricted to a limited set of situations; for limitations on input parameters, see the document on the building effect in OPS.

3.2 Receptor file

OPS supports calculations for specific points that are not on a grid, at least, not necessarily on a grid. The coordinates of these points, together with their name and sequence number, are stored in the receptor file. The coordinates must be given in the **RDM** system (unit metres). The **Create file** function can assist in making receptor files.

- A data record in the receptor file is in free format (separated by spaces or tabs).
- Data records may be preceded by one or more header records, which must contain the same number of words as a data record.
- The data record format occurs in a basic form:
ID, description, x, y

ID : sequence number (value irrelevant, only for output file)
description : string with description (value irrelevant, only for output file)
x : x coordinate in RDM coordinate system [m], integer value
y : y coordinate in RDM coordinate system [m] , integer value.

If OPS is run from a command line, command line arguments are available that allow for a variable receptor height and/or a specific definition of z_0 and land use classes for each receptor. If these command line arguments are used, more data is needed in a record of the receptor file. For more information on these options, see section '[Command line options](#)'.

Note: these options are not available in OPS-Pro.

Here we show the data needed in the receptor file for the different options.

-varz ID, description, x, y, z
-perc ID, description, x, y, z_0 , dominant_landuse, fraction_landuse (1), ..., fraction_landuse (9)
-varz -perc ID, description, x, y, z, z_0 , dominant_landuse, fraction_landuse (1), ..., fraction_landuse (9)
-domlu this option does not change the receptor record.

z : receptor height [m]; default height 4 m.
 z_0 : roughness length at receptor location [m]
dominant_landuse : index of dominant land use at receptor location [1,2, ..., 9]
fraction_landuse (k) : fraction of land use of class k at receptor location [%].

An overview of the options -perc and -domlu and their effect on the type of land use used for deposition calculations, is given in [Table 3](#).

A table with land use class definitions can be found in [Table 1](#).

Restrictions:

- OPS-Pro **Create File** only supports files with format {ID, description, x, y}; OPS-Pro can only read this type of receptor file.
- If you do not specify z_0 and land use in the receptor file, this data is extracted from z_0 and land use maps, which are part of OPS-Pro or specified in the OPS control file.
- All data records in the receptor file must have the same format.

3.3 Diurnal Variation of Emission (DVE) file

The diurnal variation of the emission (DVE) is the relative distribution of the emission throughout the day, divided into twelve 2-hour classes. For each source, a diurnal variation code is specified in each emission record of the emission file. The OPS model distinguishes a number of standard DVEs:

- 0 continuous in time
- 1 according to the (average) industrial activity over a working day

- 2 according to the (average) heating activity for space heating (in e.g. houses, buildings); including a seasonal correction in OPS. Emissions are summed in the emission summary of the Report output under "heating"
- 3 according to the (average) traffic intensity. Emissions are summed in the emission summary of the Report output under "traffic"
- 31 according to the (average) traffic intensity of light duty vehicles
- 32 according to the (average) traffic intensity of heavy duty vehicles
- 33 according to the (average) traffic intensity of (public transport) buses
- 4 special value for evaporation emissions of NH₃ and NO_x from animal housings
- 5 special value for evaporation emissions of NH₃ and NO_x from application of manure and fertiliser
- 7 according to the (average) heating activity (in e.g. greenhouses). This is the same distribution over the year as option 2, but without the seasonal correction in OPS.

Note that DVE-codes 4 and 5 are not specified in the DVE-file but are coded in the OPS source code, because they depend on meteorological situations. More information on options 4 and 5 and on the seasonal correction for space heating can be found in the OPS-documentation.

Standard distributions are described in the file `dvepre.ops`, delivered with OPS-Pro (see below).

It is possible for users to specify their own distribution patterns in a user-defined DVE-file. The **Create File** task of OPS-Pro helps to create this file, but the file can also be created with an editor. User-defined codes must be preceded by a minus sign. Up to 999 individual patterns are possible.

Note:

- code -2 gets the same seasonal correction in OPS and emissions are summed in the emission summary of the Report output under "heating" (as code 2).
- Code -3 emissions are summed in the emission summary of the Report output under "traffic" (as code 3).

OPS can read from both a standard DVE-file and a user defined file, but OPS-Pro **Create Files** cannot mix standard and user-defined codes in one emission file. If you want to mix standard and user-defined codes in OPS-Pro, you must create the emission file in another way.

Standard diurnal variations of emission

code	0-2	2-4	4-6	6-8	8-10	10-12	12-14	14-16	16-18	18-20	20-22	22-24	description
0	100	100	100	100	100	100	100	100	100	100	100	100	continuous emissions
1	73	69	68	100	129	131	124	121	109	97	93	86	Average industrial activity
2	33	33	35	80	150	155	120	116	122	135	145	77	Average heating behaviour
3	24	16	23	150	175	121	127	154	190	112	60	48	Average traffic intensity
31	8	5	43	157	141	126	143	172	190	113	67	35	Light duty vehicles
32	12	17	82	158	161	163	167	175	131	73	41	22	Heavy duty vehicles
33	3	1	54	184	149	137	149	174	165	89	69	26	Buses (public transport)
7	33	33	35	80	150	155	120	116	122	135	145	77	Aver. heating (no season. correction)

3.4 Particle Size Distribution (PSD) file

The particle size distribution (PSD) is one of the characteristics of the emission source, but only for particulate substances. It is the relative distribution of the number of particles over 6 size classes.

particle size class		1	2	3	4	5	6
size range	µm	< 0.95	0.95 - 2.5	2.5 - 4	4 - 10	10 - 20	> 20

The OPS model distinguishes three standard distributions: fine (code 1), medium (code 2) and coarse (code 3). The distributions are described in a file `pmdpre.ops`, delivered with OPS-Pro; see below.

It is possible for users to specify their own distribution patterns in a user-defined PSD-file. The **Create File** task of OPS-Pro helps to create this file, but the file can also be created with an editor. User-defined codes must be preceded by a minus sign. Up to 999 individual patterns are possible.

Note that the distribution over the size classes should be the distribution in which the substance leaves the chimney. The reason behind this is the considerably shorter lifetime of larger particles of the substance compared with small particles, changing the distribution in favour of the small particles with time.

Standard particle size distributions

code	class1	class2	class3	class4	class5	class6	description
1	70.0	12.0	8.0	5.5	2.5	2.0	standard distribution, fine
2	53.0	16.0	12.0	11.5	4.2	3.3	standard distribution, medium
3	42.0	19.0	14.0	14.5	5.9	4.6	standard distribution, coarse

In the standard distribution file, also a list of distributions for economic sectors in The Netherlands and other countries is provided.

3.5 Roughness length, land use, NL mask files

With a distribution of OPS, there are several files containing roughness length (z_0) maps and land use maps at different resolutions. An overview of the land use classes is given in Table 1. Note that the effect of land use on deposition is only taken into account for SO_2 , NO_x , NH_3 in OPS (DEPAC-module).

Table 1. Land use classes used in OPS (see DEPAC report).

1	Grass land
2	Arable land
3	Permanent crops (e.g. orchards)
4	Coniferous forest
5	Deciduous forest
6	Water
7	Built-up area
8	Heather and other nature
9	Bare soil

OPS-Pro selects the resolution of z_0 and land use maps to be used, depending on the requested resolution of the output (see Table 2 below). The highest available resolution of the z_0 grid is used ($250 \times 250 \text{ m}^2$) when receptor points are specified in a receptor file (typically non gridded receptor points). Running OPS at a command line, means that the user should take care of this via the control file. If z_0 is user specified (fixed value throughout the domain) the land use is also automatically fixed at grass.

Grid cells of the z_0 and land use grid coincide with the receptor grid, when the default receptor grid over the Netherlands is used. However, if a user defined grid is defined, the user should take care that the grid centre is defined in such a way that grid cells of the output grid coincide with those of the z_0 and land use grids (see Table 2).

If grids do not coincide, OPS chooses z_0 and land use of the grid cell where the centre of an output grid cell lies.

Table 2. Relation between output resolution and resolution of z_0 / land use maps; coordinates of upper-left corner (`xul_corner`, `yul_corner`) and number of grid cells in x -, y -direction.

output resolution (m)	resolution z_0 & land use maps (m)	<code>xul_corner</code>	<code>yul_corner</code>	<code>nx</code>	<code>ny</code>
< 500	250	-35.000	673.000	1480	1740
500 - 1000	500	-35.000	673.000	740	870
1000 - 2000	1000	-35.000	673.000	370	435
2000 - 5000	2500	-35.000	673.000	148	174
> 5000	5000	-35.000	673.000	74	87

The NL mask file `basemask.ops` is used to define the land surface of the Netherlands.

3.6 Chemical conversion rate files

OPS uses two types of files to compute chemical conversion rates for SO_2 , NO_x , or NH_3 : one containing the mass of a precursor at the start of a time step, the other the mass that has been converted during a time step. These binary files are derived using the EMEP air quality model and are averaged over a year. Files are available from 2014 to the present year.

3.7 Building effect files

In order to compute the building effect, two files are needed (and distributed with OPS): an ASCII file that describes the class values of several building and emission parameters and a binary file with a table of all building effect factors for all possible combination of classes. More information in the document on the building effect at the OPS website.

3.8 Component properties file

Default physical and chemical properties are defined in the file `defcomp3.ops`. It is not used by OPS, but used by OPS-Pro to fill the text boxes from which a user can choose. It may be used as a resource file for properties of user-defined substances, when running OPS from a command line with a control file.

componentnaam

Component name

cnr

Component number

ph

Gas-particle switch. 1 = substance is gaseous, 0 = substance is on particles. The actual size distribution is determined by the emission process, which may vary from source to source.

If the substance is particulate, then all deposition parameters are related to the particle size and as such implicitly present in the model. In this case, deposition parameters have been marked "0" on the list.

mol

Molar mass of the element or compound. If the compound has no chemical meaning such as is the case for PM₁₀, the molecular weight is set at 1. In the case of particles, the molar mass is only used as a parameter to convert deposition units e.g. from $\text{g m}^{-1} \text{s}^{-1}$ into $\text{mol ha}^{-1} \text{year}^{-1}$.

rc

Surface resistance (s.m^{-1}). The surface resistances selected apply to grass vegetation. A value of 9999 means that the dry deposition process is insignificant.

rainoutr.

Scavenging ratio (average ratio of water concentration to air concentration at the onset of a shower). A scavenging ratio of 10^6 means that the wet deposition process is so efficient that the atmosphere is 'washed clean' after every shower. The factor controlling the wet deposition is then the number of showers falling during a certain period.

dg

Diffusion coefficient in air of the element or compound concerned ($\text{cm}^2.\text{s}^{-1}$). This parameter governs the wash-out rate of a substance.

rev

Reversible washout (1) or not (0). This parameter indicates whether material disappears again from a raindrop when this drop comes into cleaner ambient air (e.g. below a smoke plume).

omz(a)

CONVRATE = rate at which the substance is converted into a daughter product or disappears in a way other than by dry or wet deposition ($\%.\text{h}^{-1}$).

omz(b)

LDCONVRATE = light dependent chemical conversion rate ($\%/h / (\text{W}/\text{m}^2)$). Total conversion rate = CONVRATE + LDCONVRATE $\times Q$, with Q = global radiation [W/m^2].

The deposition and conversion processes for SO₂, NO_x and NH₃ are defined within the OPS model and also include the production and fate of secondary products such as SO₄²⁻, NO₃⁻ and NH₄⁺. Dry deposition parameters for the different compounds are taken from the DEPAC module. The parameter values given in the list for these compounds are indicative approximations only.

4 Output files

OPS has two standard output files, the **Report** output file (PRNFILE) and a plot file (PLTFILE), which may appear in two forms:

- a **Map** output file - for receptors on a grid
- a tabulated output file - for receptors defined in a file.

Files are in ASCII format.

4.1 PRNFILE / Report Output

The Report output file contains information about the run conditions, the mean values of concentration and deposition. If the option [Include grids/tables in Report output](#) (or INCLUDE in the OPS control file) has been specified, this file also shows data for the individual receptors.

4.2 PLTFILE / Tabulated output

The tabulated output shows a table of concentrations and depositions for all receptors. There is no specific postprocessing tool available in OPS-Pro.

4.3 PLTFILE / Map Output

The Map output file contains the information for preparing maps showing the calculated concentration and deposition grids. OPS-Pro has a simple map creator built in (accessible via **View File**). In case you want to view maps with your own mapping package, the format of the map file (APS_format) is described below.

4.4 APS format

A file in APS-format contains data matrices for each of the outputs of OPS (i.e. concentration, dry deposition, wet deposition, total deposition and, possibly, concentration of aerosol). Each matrix is preceded by a one row header that describes the data in the matrix. The header contains the following fields in this sequence:

```
year, month, day, hour, comp, unit, data source, comment, format, coordsys,
xul_corner, yul_corner, nx, ny, dx, dy.
```

The format of the header is as follows (FORTRAN notation):

```
i3,i3,i3,i3,1x,a10,1x,a10,1x,a10,1x,a22,1x,a6,1x,i2,1x,f8.3,1x,f8.3,i3,i3,1x,f8.3,1x,f8.3
```

for maximal 999 of rows or columns in a grid.

```
i3,i3,i3,i3,1x,a10,1x,a10,1x,a10,1x,a22,1x,a6,1x,i2,1x,f8.3,1x,f8.3,i4,i4,1x,f8.3,1x,f8.3
```

when the number of rows or columns in a grid is extended to max 9999.

The APS-format does not provide for a missing value specification.

year

Year represented by the data. Gets the value 0 when not applicable, f.ex. with long-term averaged meteo.

month

The numerical value of the month to which the data apply. Gets the value 0 if not used.

day

The numerical value of the day to which the data apply. Gets the value 0 if not used.

hour

The hour to which the data apply. Gets the value 0 if not used.

comp

Description of the component, i.e. SO₂, NO_x, Pb, ...

unit

The unit in which the grid values are expressed.

data source

The application that produced the data.

comment

Comments of user (optional). Here used to describe the type of OPS output (i.e. concentration, deposition, etc.).

format

The format used for storing data in the grid.

coordsys

Code referring to the grid coordinate or projection system. OPS uses the **RDM** projection for its output (code 1).

xul_corner

X-coordinate of the upper left corner of the upper left grid cell. The unit depends on the coordinate/projection system and is kilometres for the **RDM** coordinate system.

yul_corner

Y-coordinate of the upper left corner of the upper left grid cell. The unit depends on the coordinate/projection system and is kilometres for the **RDM** coordinate system.

nx

The number of grid cells in X-direction, i.e. the number of values on a row.

ny

The number of grid cells in Y-direction, i.e. the number of rows.

dx

Cell dimension in X-direction. The unit depends on the coordinate/projection system and is kilometres for the **RDM** projection.

dy

Cell dimension in Y-direction. The unit depends on the coordinate/projection system and is kilometres for the **RDM** projection.

5 Running OPS at command line, source code, compiling

This chapter describes how to run the OPS-executable from a command line; this may be used by experienced users in batch mode, if f.ex. many simulations with slightly different input files are needed. A user is advised to use OPS-Pro first to generate control files and to do some test simulations before trying to make control files manually and run the OPS-executable.

OPS-Pro users can skip this chapter.

5.1 OPS control file

In the chapter on OPS-Pro, the user was assisted in setting the relevant parameters values that control a simulation with OPS by using the Graphical User Interface (GUI) of OPS-Pro. In the end, these parameter values were saved in a so-called control file (extension .ctr). In order to be able to run OPS at a command line (without the GUI), we specify here the contents of the control file for OPS. The control file can be made manually with an editor; another way of setting up a control file is to change records of a control file that has been saved by OPS-Pro.

A record in the control file consists of two fields: a parameter name followed by a parameter value, e.g. 'COMPCODE 4'. If a value is not needed, the value field is left empty.

Important note: this chapter describes the use of the different parameters when OPS is run from a command line; this may differ in a few points from the behaviour when running OPS within OPS-Pro.

<< **lower - upper** >> denotes the permitted range of an input parameter.

See section '[Examples](#)' for examples of a control file.

-----directory layer-----

DATADIR (string): name for data directory with data for

- roughness length for NL at different resolutions: z0_jr_250_lgn7.ops, z0_jr_500_lgn7.ops, z0_jr_1000_lgn7.ops, z0_jr_2500_lgn7.ops, z0_jr_5000_lgn7.ops and for Europe: z0eur.ops.
- land use for NL at different resolutions: lu_250_lgn7.ops,
- background concentration for compname = SO₂, NH₃, NO_x and years yyyy = 1984, 1994, 2005, 2012, 2020): bg"compname"yyyy.ops.
- files for the computation of chemical conversion rates from EMEP ("compname"_mass_prec_yyyy.ops, "compname"_mass_conv_dtfac_yyyy.ops).
- default physical and chemical component properties: defcomp3.ops. Is only used by OPS-Pro to fill the text boxes from which a user can choose. It may be used as a resource file for properties of user-defined substances, when running OPS from a command line with a control file.
- default daily emission variations: dvepre.ops.
- default particle size distributions: pmdpre.ops.

-----identification layer-----

PROJECT (string): project name, which the user can use to order different runs. PROJECT is a text string (max. 80 characters) and used as a header in the Report output of OPS.

RUNID (string): run identification, which the user can use to specify information on this run. RUNID is not used by OPS.

YEAR (integer): simulation year, is used in two ways:

1. For background concentrations of SO₂, NO_x and NH₃.
 - For a year in the past → background concentrations are used for that same year. Note that there are background maps available for some specific years (1984-1994-2005-2012) and that the average level of each map is calibrated for each year between 1981 and now.
 - For a year in the future → background concentrations are used from OPS runs with long-term averaged meteo, emissions 2020.
2. For chemical conversion rates of the EMEP model.
 - For a year in the past → EMEP chemical conversion rates are used for that same year. Note that prior to 2014, EMEP conversion rates are not available and an error will occur when selecting CONVRATE = EMEP (see below) for a year prior to 2014.
 - For a year in the future → EMEP chemical conversion rates are used from an EMEP run with meteo 2009, emissions 2030.

Note that the year of the meteo files (see MTFILE) should normally be the same, but the user may decide otherwise, e.g. if long term averaged meteo is used.

-----substance layer-----

COMPCODE (integer) : component code; 1 = SO₂, 2 = NO_x, 3 = NH₃, 24 = PM₁₀. For other components, see file `defcomp3.ops`. << 0 - 27 >>

COMPNAME (string): name of component, e.g. SO₂, NO_x, NH₃, PM₁₀. The user must see to it that COMPNAME is consistent with COMPCODE. OPS uses COMPCODE to control various physico-chemical properties of a pre-defined substance, not COMPNAME.

MOLWEIGHT (real): molecular weight (or molar mass) [g/mol] << 1 - 1000 >>

PHASE (integer 0/1): 1 = gaseous, 0 = particles.

LOSS (integer 0/1): 1 = include, 0 = exclude deposition + chemical conversion

DDSPECTYPE (integer 1/2): option 1 = specify dry deposition velocity v_d , option 2 = specify surface resistance R_c . The best parameterisation is obtained with R_c because the deposition velocity can then be differentiated according to atmospheric stability. Only needed if PHASE = 1, LOSS = 1 and COMPCODE ≠ 1,2,3.

DDPARVALUE (real): dry deposition parameter, either v_d [m/s] << 10⁻⁶ - 0.034 >> or R_c [s/m] << 0 - 999999 >>. Only needed if PHASE = 1, LOSS = 1 and COMPCODE ≠ 1,2,3. Note that in the case COMPCODE = 1,2,3, OPS computes R_c and v_d internally.

WDSPECTYPE (integer, 1/2/3): option 1 = specify scavenging rate, option 2 = specify scavenging ratio. Only needed if PHASE = 1, LOSS = 1 and COMPCODE ≠ 1,2,3. If COMPCODE = 1,2,3, OPS sets WDSPECTYPE to 3 and computes a scavenging ratio internally.

WDPARVALUE (real): wet deposition parameter, either scavenging rate [%/h] << 0 - 9999 >> or scavenging ratio [-] << 0 - 9999999 >>. Only needed if PHASE = 1, LOSS = 1 and COMPCODE ≠ 1,2,3. If COMPCODE = 1,2,3, OPS computes scavenging parameters internally.

DIFFCOEFF (real): molecular diffusion coefficient of the species in air [cm²/s] << 0 - 1 >>. Only needed if PHASE = 1, LOSS = 1, COMPCODE = 1,2,3. For COMPCODE ≠ 1,2,3, OPS uses a value of DIFFCOEFF = $kM^{-0.5}$, where M is the molecular weight [g/mol] and k is a conversion constant ($k = 1 \text{ cm}^2 \text{ s}^{-1} \text{ g}^{1/2} \text{ mol}^{-1/2}$).

WASH-OUT (integer 0/1): option 1 = reversible wash-out, option 0 = irreversible wash-out. Only needed if PHASE = 1, LOSS = 1, COMPCODE = 1,2,3. For COMPCODE \neq 1,2,3, OPS sets this option to 0.

CONVRATE (string or real): either the string EMEP, an empty string or a chemical conversion rate [%/h] << 0 - 999 >>.

- If PHASE = 0 or LOSS = 0 a conversion rate is not needed: use empty string.
- If COMPCODE = 1,2,3 and PHASE = 1, LOSS = 1, specify EMEP to use chemical conversion rates from the EMEP model (available since 2014) or specify an empty string to use chemical conversion rates based on background concentration maps. The EMEP conversion rates will give better results.
- If COMPCODE \neq 1,2,3 and PHASE = 1, LOSS = 1, specify a value for the chemical conversion rate [%/h].

LDCONVRATE (real): light dependent chemical conversion rate [%/h / (W/m²)] << 0 - 99.99 >>. Total chemical conversion rate = CONVRATE + LDCONVRATE x Q, with Q = global radiation [W/m²]. Only needed if PHASE = 1, LOSS = 1 and COMPCODE \neq 1,2,3. If COMPCODE = 1,2,3, OPS uses chemical conversion rates either based on background concentration maps (< 2014) or from EMEP (\geq 2014).

-----emission layer-----

EMFILE (string): the file in which emission sources and their characteristics are specified (also called .brn-file).

USDVEFILE (string, optional): user specified daily variation emission file. If not specified, use default `dvepre.ops`. More information in section '[Diurnal Variation of Emission \(DVE\) file](#)'.

USPSDFILE (string, optional): user specified particle size distribution file. If not specified, use default `pmdpre.ops`. More information in section '[Particle Size Distribution \(PSD\) file](#)'.

EMCORFAC (real): emission correction factor (trend factor); the emissions in the emission file will all be multiplied by this factor. This is useful, for instance, in situations where the emissions are yearly averages and calculations are done for a specific period in one year, with emissions not homogeneously distributed over that year. [-] << 0.01, 9.99 >>. If empty \rightarrow no correction.

TARGETGROUP (integer array): array with selected emission categories or target group << 0 - 9999 >>. If empty \rightarrow use all emission categories.

COUNTRY (integer array): array with selected emission countries or regions << 0 - 9999 >>. If empty \rightarrow use all emission countries/regions.

-----receptor layer-----

RECEPTYPE (integer 0/1/2/3): receptor type.

0 = rectangular regular grid of receptors, domain = The Netherlands;

1 = rectangular regular grid of receptors, user defined;

2 = receptors at specific locations (e.g. measuring locations), read from file;

3 = receptors at user specific regular grid, not necessarily rectangular, read from a file.

A simple example for RECEPTYPE = 3 is given below, where a character indicates an actual receptor point (= grid cell centre) given in the receptor file and an asterisk indicates a point that is skipped in the computations and gets a missing value in the output. The receptor points have to be specified in the receptor file in alphabetical order.

```

***abcdef***
***ghijkl**
**mnopqr****
stuvw*****

```

For RECEPYPE = 2, OPS computes concentrations at a specific location; for the other RECEPYPE values, OPS computes grid cell averaged concentration (using sub receptors).

XCENTER (real): x-coordinate of centre of grid [m RDM]. Only needed for RECEPYPE = 1.
 YCENTER (real): y-coordinate of centre of grid [m RDM]. Only needed for RECEPYPE = 1.
 NCOLS (integer): number of columns in grid << 0 - 9999 >>. Only needed for RECEPYPE = 1.
 NROWS (integer): number of rows in grid << 0 - 9999 >>. Only needed for RECEPYPE = 1.
 RESO (real): grid resolution [m] << lower, 999999 >>, with lower = 100 m (RECEPYPE = 0, 3), lower = 1 m (RECEPYPE = 1). Only needed for RECEPYPE = 0, 1 or 3. For RECEPYPE 3, this must match with the distances between points given in the receptor file.
 OUTER (integer 0/1): 1 = use all receptors, 0 = only use receptors inside NL. Only needed for RECEPYPE = 0.
 RCPFILE (string): file with receptor data. Only needed for RECEPYPE = 2, 3. See section '[Receptor file](#)'.

-----meteo & surface char layer-----

ROUGHNESS (real): roughness length [m]. if ROUGHNESS > 0, ROUGHNESS is a user defined fixed roughness length for the whole domain << 0 - 3 >>. If ROUGHNESS = 0, the roughness length is read from a map in the file ZOFIELD. Note that the roughness length at a receptor can be overruled in the receptor file (OPS command line option -perc).
 ZOFIELD (string): file with map of roughness lengths in NL. Only needed if ROUGHNESS = 0.
 Note that roughness length and land use maps are available in several resolutions. The user is advised to select from the available maps, the one with the highest resolution when receptor points are specified as separate points in a file (RECEPYPE = 2), and a resolution comparable to the output resolution when the receptor points are specified by a grid (RECEPYPE = 0,1,3), but it is left to the user to choose otherwise. See section '[Roughness length, land use, NL mask files](#)'.
 LUFIELD (string): file with map of land use classes in NL. Only needed if ROUGHNESS = 0 and COMPCODE = 1,2,3. If the roughness length is fixed (ROUGHNESS > 0), then the land use class is set to grass. Note that the land use at a receptor can be overruled in the receptor file (OPS command line option -perc). Note that land uses classes are only used for the computation of canopy resistance R_c for SO₂, NH₃, NO_x.
 METEOTYPE (integer 0/1/2): 0 = interpolate meteo parameters between all meteo regions, 1 = use meteo parameters from user specified meteo region, 2 = use meteo parameters from user specified meteo file.
 MTFIELD (string): meteo file.

Meteo files as input for OPS are in the form:

```

<type><year_start><month_start><year_end><month_end>.<region>
  <type>          a0 → annual, m0 → multi-annual
  <year_start>    year number of start (last 2 digits)
  <month_start>   month number of start (1 digit, 1,...9,10=a,11=b,12=c).
  <year_end>      year number of end (last 2 digits)
  <month_end>     month number of end (1 digit, 1,...9,10=a,11=b,12=c).

```

<region> 3-digit region number (0 = NL average), see Figure 1.

examples:

a006106c.001 : annual statistics over period Jan 2006 to Dec 2006, region 1

m005114c.000 : multi-annual statistics over period Jan 2005 to Dec 2014, NL average.

The value of MTFILE depends on the option METEOTYPE; as an example, we use annual meteo statistics for the year 2016.

METEOTYPE = 0 → meteo file = *meteopath/a016116c.**; the asterisk is replaced in OPS with the meteo region used in the interpolation process.

METEOTYPE = 1 → meteo file = *meteopath/a016116c.nnn*, *nnn* three digit number of meteo region, *nnn* = 000, ..., 006, 000 = average NL, see Figure 1.

METEOTYPE = 2 → meteo file (name not restricted). Format must be the same as 'standard' meteo files. External users cannot produce meteo statistics themselves.

meteopath is the directory where the meteo files are stored.

-----output layer-----

DEPUNIT (integer): index for deposition unit << 1 - 6 >>.

1 = mmol/m²/s

2 = g/m²/s

3 = mol/ha/y

4 = kg/ha/y

5 = mmol/m²/y

6 = g/m²/y.

PLTFILE (string): name of output plot file. An already existing file will be overwritten. Be sure the output folder exists and the file is not write protected, otherwise results will not be available.

PRNFILE (string): name of output print file. An already existing file will be overwritten. Be sure the output folder exists and the file is not write protected, otherwise results will not be available.

INCLUDE (string 0/1): 1 = individual receptor values are included in the Report output. This option is not suitable if the number of receptor points is large. Note: if OPS is run with command line option -v (verbose), then INCLUDE is set to 1.

GUIMADE (integer 0/1): control file has been checked by the Graphical User Interface. The value of GUIMADE is not used by OPS.

5.2 Running OPS at the command line

OPS can run on both the Windows and Linux platforms. Note that data needed to run the model is independent of the platform; this holds also for the unformatted (binary) data. The data is available in the OPS-Pro distribution or via the OPS-website for command line users.

5.2.1 Windows

Running OPS is possible with the Windows-executable delivered with OPS-Pro (ops.exe).

- Start a command-window (type cmd in the Windows search bar)
- Change to the directory where the control file is located (*path_input*) and execute OPS (*path_exe* = directory where the executable is located):

```
> cd path_input
> path_exe/ops.exe -i control-file
```

5.2.2 Linux

For Linux, there is also a precompiled OPS executable (built under GNU/Linux version 3.10.0), downloadable from the OPS website www.rivm.nl/ops (including the data needed for OPS). The command line instructions to run the executable are the same as for Windows.

5.2.3 Command line options

- i *control-file* - specifies the name of the control-file (*.ctr). Mandatory arguments.
- r - issue release number and date.
- v - provide more output in the REPORT file (effective deposition velocity , roughness length, land use, precipitation).
- nosub - do not use sub area sources or sub receptors (for test purposes).

OPS uses maps of roughness length z_0 and percentages for each land use class in order to compute depositions at the receptor and the loss of deposited material along a trajectory; z_0 is also used for dispersion calculations. Additional command line arguments are available that allow for a variable receptor height and/or a specific definition of z_0 and land use classes for each receptor. If these command line arguments are used, more data is needed in a record of the receptor file (see section '[Receptor file](#)').

- varz - use a variable receptor height, specified in the receptor file (default = 4 m). For a receptor grid, the default receptor height is used. Note that this option does not give reliable results close to a source; it should only be used for receptors further away, where a plume has been dispersed over the mixing layer.
- perc - use percentages per land use class at the receptor, specified in the receptor file. In this case, the effective canopy resistance R_c is computed by averaging deposition velocities per land use class (weighted by the occurrence of each land use class).
- varz -perc - combine both options above.
- domlu - use dominant land use instead of percentages for each land use class, both at the receptor and along the trajectory.

If z_0 is user specified (fixed value throughout the domain) the land use is also automatically fixed to grass. Note that the effect of land use on deposition is only taken into account for SO_2 , NO_x , NH_3 in OPS. An overview of the options -perc and -domlu and their effect on the type of land use used for deposition calculations, is given in Table 3 below.

Table 3. Options -perc, -domlu and their effect on the type of land use for deposition calculations.

- fractions → use fraction of each land use class (weighted averaged deposition)
- dominant → use dominant land use class (fractions are not used)
- map → use land use map
- receptor file → use land use data from receptor file.

options	land use at receptor, receptor grid	land use at receptor, defined in a file	land use along a trajectory
	fractions-map	fractions-map	fractions-map
-perc	fractions-map	fractions-receptor file	fractions-map
-domlu	dominant-map	dominant-map	dominant-map
-perc -domlu	dominant-map	dominant-receptor file	dominant-map

5.3 Source code, compiling

The OPS source code can be downloaded from the repository github.com/rivm-syso/ops. Compiling options for the Intel Fortran compiler `ifort` are given below.

5.3.1 Windows - Intel compiler options

Debug version: `/nologo /debug:full /Od /fpp /warn:interfaces /assume:byterecl /module:"Debug\\" /object:"Debug\\" /Fd"Debug\vc100.pdb" /traceback /check:all /libs:static /threads /dbglibs /c`

Release version: `/nologo /O2 /fpp /assume:byterecl /module:"Release\\" /object:"Release\\" /Fd"Release\vc100.pdb" /libs:static /threads /c`

5.3.2 Linux - Intel compiler options

Debug version: `-nowarn -DUNIX -fpp -assume byterecl -check bounds -debug-parameters all -traceback -O0 -g -fpe0 -extend_source -gen-interfaces -warn interfaces`

Release version: `-nowarn -DUNIX -fpp -assume byterecl -O2 -fpe0 -extend_source -gen-interfaces -warn interfaces`

6 Examples

Two examples are provided that illustrate step by step how to proceed to obtain the answer on the formulated problems, using OPS-Pro. After you finished your classes making the examples you can check the results to reference output in the zip-file “examples.zip” in the folder where OPS-Pro is installed.

When using the Linux environment, you can use the input files provided in the zip-file “examples.zip” included in the zip-file with the OPS-Linux distribution at the OPS-website. You will have to change all pathnames “\$PATH_OPS_Linux” in the ctr-files according to those where you installed OPS on your Linux system.

The examples are the same for both environments.

To complete the examples you should create a folder ‘examples’ in the directory where OPS-Pro is installed (in the examples C:\Applics\OPS-Pro_2020\examples has been used).

6.1 Example 1, industrial point source

Problem: Industrial point source, located in The Netherlands at RDM-coordinates [128730, 432028], with a stack height of 25 m and a heat content of 1 MW. This source emits continuously gaseous hydrogen fluoride (HF) with a rate of 10 g/s. Calculate the yearly average HF concentration and deposition around this source in an area of 7.5 x 7.5 km², with a spatial resolution of 500 m. Use long-term average meteorological conditions and a fixed roughness value of 0.25 m.

Solving the problem with OPS-Pro consists of three steps:

Step 1: Creating the emission file

Step 2: Defining the run

- a: Setting the General parameters
- b: Setting the Emission parameters
- c: Setting the Receptor parameters
- d: Setting the Meteo and roughness parameters

Step 3: Running the job, viewing its progress and output

Step 1: Creating the emission file

- 1 Choose **Create File** in the task bar.
- 2 Leave **Emission** as file type.
- 3 Select HF (fluorine) - gas in the combo box labelled **Component name**. Once you have done this, the check box labelled **Gaseous** will be checked and greyed. Also the combo box **Particle size** will have become inaccessible because particle size does not apply to gases.
- 4 Type the values for X- and Y-coordinate, emission strength, heat content and source height in the appropriate text boxes. Because it concerns a point source, **SD Height** and **Source diameter** are not relevant and get the value 0.
- 5 Select **Continuous emission** from the combo box **Diurnal variation**.
- 6 Choose **File>Save** to open the **Save as** dialog. Enter a name in the box labelled **File name**, for instance `example1.brn`, browse to the folder `C:\Applics\OPS-Pro_2020\Examples` and press the **Save** button.

OPS-Pro 2020

File Edit Options Help

Define Run
View File
Create File
Show Progress

File type

Emission Diurnal variation
 Receptor Particle size distribution

Emission

X-coordinate (m.): 128730
Y-coordinate (m.): 432028
Emission strength (g/s): 10
Heat content (MW): 1
Source height (m.): 25
SD height (m.): 0
Source diameter (m.): 0

Diurnal variation: Continuous emission User-defined
Particle size: User-defined
Target group: Other industry
Region/Country: NETHERLANDS
Component name: HF (fluorine)- gas. Gaseous

Copy Previous

Record 1/1

Activat

Step 2a: Defining the General parameters


- 1 Choose **Define Run** in the task bar. A tab book of 4 pages appears.
- 2 Select the first tab, labelled **General**.
- 3 Type the **Project name**. The project name will be used to identify the Report output. Type f. ex. First example of an OPS-Pro application.
- 4 Type the **Run-identifier**. The run-id is used in naming the OPS output files by extending the run-id with the appropriate extension. Type f.ex. example1.
- 5 Select the **component** HF (fluorine) - gas from the list displayed by the **Component** combo box.
- 6 Type a year in the future in the textbox **Year**, f.ex. 2030. This will invoke long term averaged meteorological conditions.
- 7 Leave **Unit of deposition** at its default value (mol/ (ha . y)).
- 8 Select the desired **Output directory**. Here we will use C:\Applics\OPS-Pro_2020\Examples.
- 9 Check the box **Include grids/tables in text output**. This ensures that the individual receptor values are included in the Report output.


The screenshot shows the OPS-Pro 2020 software window with the 'Define Run' dialog box open. The 'General' tab is selected, and the following parameters are entered:

- Project name (max. 56 characters):** First example of an OPS-Pro application
- Run-identifier used for file naming (max. 76 characters):** example1
- Component:** HF (fluorine)- gas.
- Year:** 2020
- Unit of deposition:** mol/(ha.y)
- Output directory:** C:\Applics\OPS-Pro_2020\examples\
- Include grids/tables in text output.
- Verbose output.
- Background execution.

The 'Next >' button is highlighted in blue, indicating the next step in the process.

Step 2b: Setting the Emission parameters

- 1 While in the **Define Run** modus, click the tab **Emission**.
- 2 Click the  button next to the field **Emission file** and search for the file `example1.brn`. In Step 1 this file has been saved in the directory `C:\Applics\OPS-Pro_2020\Examples`. After the emission file has been selected, OPS-Pro scans the emission file to see whether it contains codes for user-defined diurnal variations and or particle size distributions. Because this is not so, the corresponding text boxes stay disabled.
- 3 Leave the selections for **target group** and **country/region** at their default settings, being `all`.
- 4 Leave the check box for the **emission correction factor** unchecked.



Step 2c: Setting the Receptor parameters

- 1 While in the **Define Run** modus, click the tab **Receptor**.
- 2 Select the 2nd receptor type option, being **Midpoints of the grid cells of a grid specified by the user**.
- 3 As the receptor grid should centre around the source, enter the source's **X-** and **Y-** coordinate values in the corresponding fields.
- 4 Enter 500 in the field labelled **Grid cell dimension**.
- 5 As the receptor field should span 7.5 kilometres in both directions, enter 15 for both **Number of cells horizontally** and **Number of cells vertically**.

The screenshot shows the OPS-Pro 2020 software interface. The window title is "OPS-Pro 2020" and the menu bar includes "File", "Edit", "Options", and "Help". The main window is divided into a left sidebar and a main content area. The sidebar contains four buttons: "Define Run" (highlighted in blue), "View File", "Create File", and "Show Progress". The main content area has a tabbed interface with "General", "Emission", "Receptor", and "Meteo and roughness" tabs. The "Receptor" tab is active, showing the following configuration options:

Receptortype

- Midpoints of the grid cells of a grid covering the Netherlands.
- Midpoints of the grid cells of a grid specified by the user.
- Defined in a file.


Grid specification

X-coordinate of grid midpoint (m): 128730	Y-coordinate of grid midpoint (m): 432028	Grid cell dimension, both directions (m): 500
Number of cells horizontally: 15	Number of cells vertically: 15	<input type="checkbox"/> Include gridpoints outside the Netherlands.

At the bottom of the window, there are two checkboxes: Verbose output. and Background execution. To the right of these checkboxes are three buttons: "< Previous", "Next >", and "Finish". The status bar at the bottom left shows "Local run" and the bottom right shows "Activa".

Step 2d: Setting the Meteo and roughness parameters

- 1 While in the **Define Run** modus, click the tab **Meteo and roughness** or, coming from step 2c, click the **Next** button.
- 2 In the panel **Type of meteostatistics**, select **Standard meteo - Varying between receptors**.
- 3 Select **Long term annual average 2005-2014, The Netherlands** from the combo box **Meteorological period** (normally, this should already be selected because selecting a year in the future on the **General** tab - Step 2a, enforces long term averaged meteo, but sometimes this does not work properly).
- 4 In the panel **Surface roughness**, select **The same value for all receptors** and enter the value **0.25** in the adjacent textbox.



Step 3: Running the job, viewing its progress and output

Before running the job you have to decide whether to run the job in the foreground or in the background. In the foreground means that you cannot specify and run other jobs while this job is running; in the background means that you can specify and run other jobs as soon as this job is submitted. In this example we will use foreground execution, leaving the check box **Background Execution** unchecked.

Press the **Finish** button to start this run.

After pressing **Finish** the run parameters are saved in the control file, which is stored in the output directory (see Step 2a). Subsequently OPS is started with this control file as input. A pop-up appears in which the progress of the job is displayed. As soon as the job has finished, another window pops up asking you whether you want to view the output files. After clicking Yes, OPS-Pro switches to the **View File** modus and opens the output. The output is displayed in a tab book with two tabs: one for the Report output and one for the Map output. Click the **Report** tab and then choose **File>Print** to print the report of this job. Compare the calculated concentrations and depositions with the reference output in the zip-file.

6.2 Example 2, industrial point source, user defined particle size distribution

Problem: Industrial point source emitting lead (Pb) and situated in the Rijnmond area at RDM-coordinates [80000, 435000]. Stack height 40 m, no heat content. This source emits at an average rate of 1 g/s and shows a typical industrial diurnal emission cycle. The particle size distribution of the lead particles as emitted by this source does not fit into the standard distributions as available in OPS and is as follows:

0-0.95 μm : 40%; 0.95-4 μm : 20%; 4-10 μm : 20%; 10-20 μm : 10%; > 20 μm : 10%.

Calculate the yearly average Pb concentration and deposition at 4 locations in the Rijnmond area, being (coordinates in square brackets):

Vlaardingen [82000; 436400]

Rockanje [64500; 432500]

Maasdijk [75000; 441800]

Poortugaal [86000; 430000]

Use long-term average meteorological conditions and receptor point specific roughness values.

Solving the problem consists of three steps:

Step 1: Creating the required input files

- a: Creating the particle size distribution file
- b: Creating the emission file
- c: Creating the receptor file

Step 2: Defining the run

- a: Setting the General parameters
- b: Setting the Emission parameters
- c: Setting the Receptor parameters
- d: Setting the Meteo and roughness parameters

Step 3: Running the job, viewing its progress and output

Step 1a: Creating the particle size distribution file

You must start with this file because a non-standard particle size distribution file is needed in creating the emission file.

- 1 Choose **Create File** in the task bar.
- 2 Select Particle size distribution as **file type**.
- 3 Enter a **Code** for the **Particle size distribution**. User specified distributions must have a code between -1 and -999 . Because the numbers -1 , -2 and -3 are reserved for your own definitions of the standard distributions 'fine', 'intermediate' and 'course', enter -4 .
- 4 Enter a **Description** for this distribution, f.ex. 'industrial lead aerosol' (without quotes).
- 5 Now enter the values 40, 20, 20, 10, 10, 0 for the classes 1 to 6, respectively.
- 6 Choose **File>Save** to open the **Save as** dialog. Enter a name in the box labelled File name, for instance `example2.psd`, browse to the folder `C:\Applics\OPS-Pro_2020\Examples` and press the **Save** button.

The screenshot shows the OPS-Pro 2020 software interface. The 'Create File' option is selected in the left-hand menu. The main window displays the 'Particle size distribution' configuration form. The 'File type' section has 'Particle size distribution' selected. The 'Code' is set to -4, and the 'Description' is 'industrial lead aerosol'. The particle size distribution classes are defined as follows:

Class	Value (%)
Class 1, < 1 μm :	40
Class 2, 1-2.5 μm :	20
Class 3, 2.5-4 μm :	20
Class 4, 4-10 μm :	10
Class 5, 10-20 μm :	10
Class 6, >20 μm :	0

At the bottom of the form, there are navigation controls for 'Record 1/1'.

Step 1b: Creating the emission file

The **Create File** modus is already active, so you can start with choosing the file type.

- 1 Select **Emission** as **file type**.
- 2 Select **Pb(lead) - aer.** in the combo box labelled **Component name**. Once you have done this, the check box labelled **Gaseous** will be greyed.
- 3 Type the values for X- and Y-coordinate, emission strength, heat content and source height in the appropriate text boxes. Because it concerns a point source, **SD Height** and **Source diameter** are not relevant and get the value 0.
- 4 Select **Average Industrial Activity** from the combo box **Diurnal variation**.
- 5 Check the box **User-defined** at the right of the **Particle size** combo box. The **Open** dialog is displayed. Select the psd file that you have created in the previous step and click on the button **Open**.
- 6 Select the particle size distribution for this source from the **Particle size** combo box. Because the psd file you have opened contains only one distribution, only one distribution can be selected: **industrial lead distribution**.
- 7 Select **Other industry** from the combo box **Target Group** and **Netherlands** from the combo box **Region/Country**.
- 8 Choose **File>Save** to open the **Save as** dialog. Enter a name in the box labelled **File name**, for instance **example2.brn**, browse to the folder **C:\Applics\OPS-Pro_2020\Examples** and press the **Save** button.

OPS-Pro 2020

File Edit Options Help

Define Run

View File

Create File

Show Progress

File type

Emission Diurnal variation

Receptor Particle size distribution

Emission

X-coordinate (m.): 80000

Y-coordinate (m.): 435000

Emission strength (g/s): 1

Heat content (MW): 0

Source height (m.): 40

SD height (m.): 0

Source diameter (m.): 0

Diurnal variation: Average industrial activity User-defined

Particle size: industrial lead aerosol User-defined

Target group: Other industry

Region/Country: NETHERLANDS

Component name: Pb (lead) - aer. Gaseous


Copy Previous

Record 1/1

Step 1c: Creating the receptor file

The **Create File** modus is still active, so you can start with choosing the file type.

- 1 Select **Receptor** as **file type**.
- 2 Type the name of the first receptor point, Vlaardingen, in the box labelled **Description** and the Vlaardingen coordinates in the boxes **X-coordinate** and **Y-coordinate**, respectively. Then click the ► button to proceed to the next record. Fill in name and coordinates of the 2nd receptor point, click ► and so on, until all receptors are specified.
- 3 Choose **File>Save** to open the **Save as** dialog. Enter a name in the box labelled **File name**, for instance `example2.rcp`, browse to the folder `C:\Applics\OPS-Pro_2020\Examples` and press the **Save** button



Step 2a: Defining the General parameters



- 1 Choose **Define Run** in the task bar. A tab book of 4 pages appears.
- 2 Select the first tab, labelled **General**.
- 3 Type the **Project name**. The project name will be used to identify the Report output. Type f.ex. Second example of an OPS-Pro application.
- 4 Type the **Run-identifier**. The run-id is used in naming the OPS output files by extending the run-id with the appropriate extension. Type f.ex. example2.
- 5 Select the component **Pb (lead) - aer.** from the list displayed by the **Component** combo box.
- 6 Type a year in the future in the textbox **Year**, f.i. 2020. This will invoke long term averaged meteorological conditions.
- 7 Leave **Unit of deposition** at its default value ($\text{mol}/(\text{ha} \cdot \text{y})$).
- 8 Select the desired **Output directory**. Here we will use `C:\Applics\OPS-Pro_2020\Examples`.
- 9 Check the box **Include grids/tables in text output**. This ensures that the individual receptor values are included in the Report output.


The screenshot shows the 'OPS-Pro 2020' application window. The 'Define Run' dialog is open, with the 'General' tab selected. The dialog contains the following fields and options:

- Project name (max. 56 characters):** Second example of an OPS-Pro application
- Run-identifier used for file naming (max. 76 characters):** example2
- Component:** Pb (lead) - aer.
- Year:** 2020
- Unit of deposition:** mol/(ha.y)
- Output directory:** C:\Applics\OPS-Pro_2020\examples\
- Include grids/tables in text output
- Verbose output.
- Background execution.


Navigation buttons at the bottom right include '< Previous', 'Next >', and 'Finish'. The status bar at the bottom left indicates 'Local run'.


Step 2b: Setting the Emission parameters

- 1 While in the **Define Run** modus, click the tab **Emission**.
- 2 Click the  button next to the field **Emission file** and search for the file `example2.brn`. In Step 1 this file has been saved in the directory `C:\Applics\OPS-Pro_2020\Examples`. After the emission file has been selected, OPS-Pro scans the emission file to see whether it contains codes for user-defined diurnal variations and or particle size distributions. As a result the text box labelled **File with user-defined particle size distributions** becomes active, because in this example a user-defined particle size distribution is used.
- 3 Click on the  button to start browsing for the psd file in which the user-defined particle size distribution is described. In step 1 this file has been saved as `example2.psd` in the directory `C:\Applics\OPS-Pro_2020\Examples`.
- 4 Leave the selections for **target group** and **country/region** at their default settings, being `all`.
- 5 Leave the check box for the **emission correction factor** unchecked.




Step 2c: Setting the Receptor parameters

- 1 While in the **Define Run** modus, click the tab **Receptor** or, coming from step 2b, click the **Next** button.
- 2 Select the 3rd receptor type option, **Defined in a file**. Subsequently, select **Use own file**.
- 3 Click the  button and select the file `example2.rcp` in the **Open** dialog. `Example2.rcp` was created in Step 1c and stored in the directory `C:\Applics\OPS-Pro_2020\Examples`.



Step 2d: Setting the Meteo and roughness parameters

- 1 While in the **Define Run** modus, click the tab **Meteo and roughness** or, coming from step 2c, click the **Next** button.
- 2 In the panel **Type of meteostatistics**, select **Standard meteo - Varying between receptors**.
- 3 Select **Long term annual average 2005-2014, The Netherlands** from the combo box **Meteorological period** (normally, this should already be selected because selecting a year in the future on the **General** tab - Step 2a, enforces long term averaged meteo, but sometimes this does not work properly).
- 4 In the panel **Surface roughness**, select **Varying between receptors**.



Step 3: Running the job, viewing its progress and output

Before running the job you have to decide whether to run the job in the foreground or in the background. In the foreground means that you cannot specify and run other jobs while this job is running; in the background means that you can specify and run other jobs as soon as this job is submitted. In this example we will use foreground execution, leaving the check box **Background Execution** unchecked.

Press the **Finish** button to start this run.

After pressing **Finish** the run parameters are saved in the control file, which is stored in the output directory (see Step 2a). Subsequently OPS is started with this control file as input. A pop-up appears in which the progress of the job is displayed. As soon as the job has finished another window pops up asking you whether you want to view the output files. After clicking Yes, OPS-Pro switches to the **View File** modus and opens the output. The output is displayed in a tab book with two tabs: one for the Report output and one for the Map output. Click the **Report** tab and then choose **File>Print** to print the report of this job. Compare the calculated concentrations and depositions with the reference output in the zip-file.